



QWC-004 Firmware update process.

Description: Update to version 8.15

Items Needed: Windows 10 PC

Software needed: Firmware Utility and Firmware file.

**File for download**

[ftp://qomo08.pointto.us/DocumentCameras/QWC-004/Firmware/QWC004\\_200815.zip](ftp://qomo08.pointto.us/DocumentCameras/QWC-004/Firmware/QWC004_200815.zip)


Published Date: 10/1/2020

**Prerequisite:**

- 1) Disable or disconnect any other camera device connected or built into computer. For integrated webcams in laptops disable via device manager.

**Section 1: Firmware update**

- 1) Download all files specified and unzip to unzip to a folder.
- 2) Connect the QWC-004 webcam device to computer via USB
- 3) Run USB\_XU\_BurnerAP utility.



- 4) Press the “Browse” button and select SRC file (for example: CHROMEBOOK\_60H---V200815\_K0\_06-ZXCZ-QOMO.SRC)
- 5) Press “GO” button and wait for completed green bars.

